

DockingFrames 1.1.0 - Core

Benjamin Sigg

February 20, 2011

Contents

1	Introduction	5
1.1	Use cases	5
1.2	Other frameworks	5
1.3	Notation	6
1.4	Design principles	7
1.5	Numbers	7
2	Basics	9
2.1	Hello World	9
2.2	Dockable	10
2.3	DockStation	10
2.3.1	StackDockStation	11
2.3.2	SplitDockStation	12
2.3.3	FlapDockStation	13
2.3.4	ScreenDockStation	13
2.4	DockController	14
2.5	DockFrontend	15
2.5.1	Close-Button	16
2.5.2	Storing the layout	16
3	Load and Save layouts	17
3.1	Placeholders	17
3.2	Local: DockableProperty	18
3.2.1	Creation	18
3.2.2	Usage	19
3.2.3	Storage	20
3.3	Global: DockSituation	20
3.3.1	Basic Algorithms	20
3.3.2	Basic Usage	22
3.3.3	Reuse existing Dockables	23
3.3.4	Extract local information	25
3.4	Perspectives	25
3.5	DockFrontend	26
3.5.1	Local	26
3.5.2	Global	26
3.5.3	Missing Dockables	27
4	Actions	29
4.1	Show Actions	30
4.1.1	List of Actions	30
4.1.2	Source of Actions	30
4.2	Standard Actions	31
4.2.1	Simple actions	32
4.2.2	Group actions	32
4.3	Custom actions	34
4.3.1	Reuse existing view	34
4.3.2	Custom view	35

5	Titles	37
5.1	Lifecycle	37
5.2	Custom titles	38
5.2.1	Implementing a new title	38
5.2.2	Apply the title	39
6	Themes	40
6.1	Existing Themes	40
6.1.1	NoStackTheme	40
6.1.2	BasicTheme	40
6.1.3	SmoothTheme	41
6.1.4	FlatTheme	41
6.1.5	BubbleTheme	41
6.1.6	EclipseTheme	42
6.2	Customize DockThemes	43
6.2.1	UI-Properties	43
6.2.2	Colors	44
6.2.3	Fonts	45
6.2.4	Icons	46
6.2.5	Actions	46
6.2.6	Titles	46
6.2.7	Displayers	46
6.3	Custom Theme	46
7	Drag and Drop	48
7.1	Relocator	48
7.2	Sources	48
7.2.1	DockElementRepresentative	48
7.2.2	Remote control	49
7.3	Destinations	49
7.3.1	Search	50
7.3.2	Drop	50
7.4	Influences	51
7.4.1	Modes	51
7.4.2	Restrictions	51
8	Preferences	53
8.1	Model	53
8.1.1	Preference	53
8.1.2	PreferenceModel	54
8.1.3	PreferenceTreeModel	54
8.2	View	54
8.2.1	Editors	55
8.2.2	Operations	55
8.3	Storage	55
8.4	Lifecycle	56
9	Extensions	58
9.0.1	Glass Extension	58
9.0.2	Extension Points	58

10 Properties	59
10.1 Themes	59
10.2 Stations	60
10.3 Controlling	62
10.4 Legacy	63
10.5 Gimmicks	63

1 Introduction

DockingFrames is an open source Java Swing framework published under the LGPL (lesser GNU public license). This means you are allowed to use **DockingFrames** in any way you like. However if you modify the framework you are required to distribute the modified source code together with your new library.

DockingFrames consists of two projects, **Core** and **Common** (the libraries **dockingFramesCore.jar** and **dockingFramesCommon.jar**). **Core** provides the basic functionality of the framework while **Common** adds features to make the life of developers and users easier. It is possible to use **Core** alone, but in most cases you are better of using both projects together.

This document introduces you to the basic concepts of **Core**. Naturally it cannot cover all the details, you should also have a look into the API documentation

<http://dock.javaforge.com/doc.html>, the tutorial project and the forum on <http://forum.byte-welt.net/>.

1.1 Use cases

What does the framework do? **DockingFrames** manages the layout of your graphical user interface. It allows the user to rearrange your user interface in the way he or she likes it. All you need to do is to group your controls in small panels (called **Dockables**).

For which application can it be used? In general one can say that bigger applications profit more than small ones. Also power-users will like the flexibility to set up “their” user interface, the common user however might be overwhelmed by all the buttons and options. A typical use-case would be an application which can present so many data to the user that one screen is not enough. With a modifiable user interface the user can easily filter the data and blend out the graphs, panels and buttons he does not need.

1.2 Other frameworks

There are at least 10 other docking frameworks for Java. As with any complex software it is impossible to say which of them is the best one. But there are some features which make sure **DockingFrames** is one of the better ones:

- The licence, you can use the framework without paying a fee nor are you required to open source your entire project.
- It is pure **Swing**, it does not have any dependencies to other libraries. It does not force you to use some special design pattern or set up some cryptic configuration files.
- It does support unsigned applets (does anyone use them anymore?) and webstart.
- Multiple instances can run independent from each other. Sounds trivial, but there are many libraries which cannot handle this case. This design has benefits, for example a preference dialog can easily show a preview.

The preview is just another instance and any properties only affects this independent instance.

- Much control for the client. You can change almost anything to your likings. Unfortunately this is not always easy as some properties are hidden deep in the framework. On the bright side you are now reading the document which tells you how to modify some of the modules.

1.3 Notation

This document uses the following style-guide:

- “Technical things” like class names and project names are written mono-spaced like this: `java.lang.String`.
- Packages are not written. Almost all classes and interfaces have a unique name and with the help of the API documentation you should be able to find them easily.
- “The client” is the application using `DockingFrames`. “The developer” is you. “The user” is a sentient beeing using “the client”, this might even be yourself.
- Additional information is given in boxes like the ones below.



Tips and tricks are listed in boxes.



Important notes and warnings are listed in boxes like this one.



Implementation details, especially lists of class names, are written in boxes like this.



These boxes explain *why* some thing was designed the way it is. This might either contain some bit of history or an explanation why some awkward design is not as bad as it first looks.



Examples in the tutorial application are mentioned in these boxes.

1.4 Design principles

In order to understand **Core** it helps to know what the basic design is. These design principles are applied through the entire framework. Most modules follow this principles, although there are a few exceptions in old code.

- The usage of **static** variables is discouraged. There are no global variables, all components must be built in a way that multiple instances can be run by the same classloader at the same time independently from each other.
- Communication through interfaces and usage of factories. Especially newer code makes heavy use of factories and interfaces to keep classes independent from each other. This also means that the keyword **instanceof** is to be used rarely.
- Strong typesafety. For the client is should be impossible to smuggle an object of the wrong type into the framework, there should never be a **ClassCastException**.
- Apply properties eagerly. This means that if the client changes some property it is applied before the client continues its work. This makes some parts of the framework more complex, but in the long run it adds a lot of flexibility.

1.5 Numbers

In **Core**, there are about 50'000 lines of code, distributed in over 1200 classes and interfaces. You don't need to know all of them to get your first application to run. Ordered by their semantics, the classes can be collected in groups:

Control group Long living objects which control the behavior of the user interface. For example the object handling drag & drop is created once and remains until the application shuts down.

Swing tree group Objects that are actually seen by the user because they are some kind of **java.awt.Component**. These objects build a tree, the objects from the **control group** can be seen as roots in this tree. Clients, or the framework itself, frequently reorganizes this tree.

Theme group Objects responsible for painting the user interface. Sometimes these classes are big and complex, but they never are important. They can always be replaced with some other painting code.

Support group Various small classes which do not fit into the other groups. These objects often have a short lifetime and can do exactly one task. A factory would be a good example.

Comparing the sizes (number of lines) of these groups the following numbers are seen:



Control group	10%
Swing tree group	30%
Theme group	20%
Support group	40%

2 Basics

The basic idea of **Core** is to have one object that controls the framework, one object for each floating panel and one object for each area where a floating panel can be docked.



The controller is a **DockController**, the floating panels are **Dockables** and the dock-areas are **DockStations**.

2.1 Hello World

Let's start with a simple hello world. This application uses the three basic components, the example consists of valid code and can run:

```
1 import javax.swing.JFrame;
2
3 import bibliothek.gui.DockController;
4 import bibliothek.gui.dock.DefaultDockable;
5 import bibliothek.gui.dock.SplitDockStation;
6 import bibliothek.gui.dock.station.split.SplitDockGrid;
7
8 public class HelloWorld {
9     public static void main( String[] args ) {
10         DockController controller = new DockController();
11
12         SplitDockStation station = new SplitDockStation();
13         controller.add( station );
14
15         SplitDockGrid grid = new SplitDockGrid();
16         grid.addDockable( 0, 0, 2, 1, new DefaultDockable( "N" ) );
17         grid.addDockable( 0, 1, 1, 1, new DefaultDockable( "SW" ) );
18         grid.addDockable( 1, 1, 1, 1, new DefaultDockable( "SE" ) );
19         station.dropTree( grid.toTree() );
20
21         JFrame frame = new JFrame();
22         frame.add( station.getComponent() );
23
24         frame.setDefaultCloseOperation( JFrame.EXIT_ON_CLOSE );
25         frame.setBounds( 20, 20, 400, 400 );
26         frame.setVisible( true );
27     }
28 }
```

What happens here? In line 10 a **DockController** is created. The controller will handle things like drag and drop. All elements will be in his realm. In line 12 a new **DockStation** is created and in line 13 this station is registered as root station at the **DockController**.

Then in line 15-19 a few children for **station** are generated. To set the layout of those children a **SplitDockGrid** is used. **SplitDockGrid** takes a few **Dockables** and their position and puts this information into a form that can be understood by **SplitDockStation** (line 19). It would be possible to add the **Dockables** directly to the station, but this is the easy way.

In line 21 a new frame is created and in line 22 our **DockStation** is added to the frame.



More demonstration applications can be found in the archive-file of **DockingFrames**. The demonstrations are stored in the project called “tutorial“. You can use the ”tutorial.sh“ or ”tutorial.bat“ file to start them.



Another ”hello world“ can be found in the tutorial application under ”Basics/Core/Hello World“.

2.2 Dockable

A **Dockable** represents a floating panel, it consists at least of some **JComponent** (the panel it represents), some **Icon** and some text for a title. Each **Dockable** can be dragged by the user and dropped over a **DockStation**.

Clients can implement the interface **Dockable**, but it is much less painful just to use **DefaultDockable**. A **DefaultDockable** behaves in many ways like the well known **JFrame**: title, icon and panel can be set and replaced at any time.

A small example:

```
1 DefaultDockable dockable = new DefaultDockable();
2 dockable.setTitleText( "I'm_a_JTree" );
3 Container content = dockable.getContentPane();
4 content.setLayout( new GridLayout( 1, 1 ) );
5 content.add( new JScrollPane( new JTree() ) );
```



If implementing **Dockable**, pay special attention to the API-doc. Some methods have a rather special behavior. It might be a good idea to subclass **AbstractDockable** or to copy as much as possible from it.



A careful analysis of **Dockable** reveals that there is no way for applications to store their own properties within a **Dockable** (unless using a subclass...). There are two reasons for this.

First: if only using the default implementation, then clients do not have to worry about these properties. Storage of properties must and will be handled by the framework itself.

Second: Components of the framework cannot get any unfair advantage over custom components. Everything has to be designed in a way that it can work with new and unexpected implementations of **Dockable**.

2.3 DockStation

Dockables can never fly around for themselves, they need a **DockStation** as anchor point. The relationship between **DockStation** and **Dockable** can best be

described as parent-child-relationship. A `DockStation` can have many children, but a `Dockable` only one parent.

There are some classes which are `DockStation` and `Dockable` at the same time. They allow to build a tree of `DockStations` and `Dockables`. A controller can handle more than just one tree and `Dockables` can switch from one tree to another.

Clients can implement new `DockStations`. But be warned that the interface contains many methods and a lot of them require a lot of code. Don't expect to write less than 1000 lines of code.

A small example that builds a `StackDockStation`:

```
1 StackDockStation stack = new StackDockStation();
2 stack.setTitleText( "Stack" );
3 stack.drop( new DefaultDockable( "One" ) );
4 stack.drop( new DefaultDockable( "Two" ) );
```

Some observations: `StackDockStation` is a `Dockable` as well, in line 2 the title is set. Two `DefaultDockables` are put onto the station in lines 3,4, the method `drop` is available in all `DockStations`.




`DockStations` are the most complex classes within the framework, they are also among the most important classes. It is very uncommon to subclass them or to write new ones. If you think you need to subclass a `DockStation`, be sure to have explored all other options.

`Core` offers a collection four different stations. These are listed in the remainder of this section.

2.3.1 `StackDockStation`

This station is organized like a `JTabbedPane`. Only one child is visible, but another can be made visible by clicking some button. The framework will automatically create new `StackDockStations` when a `Dockable` is dragged over another. Also `StackDockStations` with only one child get automatically replaced by this child.


The station consists of four layers, as seen in the image below. There is a background panel (1) which just is some **Container** to put other things onto it. Then there is a selection layer (2), which is represented by an instance of **StackDockComponent**. Above that is a **DockableDisplayer** (3) for each **Dockable**. The displayers paint some decorations that depend on the **Dockables** in the topmost layer (4).



2.3.2 SplitDockStation


All the children of this station are visible. The user controls the children as if the station would consist of many **JSplitPanes** set into each other (hence the name). Internally the station is organized as tree, where a leaf is a **Dockable** and a node the gap between two sets of **Dockables**. Furthermore this station offers a “fullscreen mode” where one of its children takes up the entire space and all other children are invisible.

Like the **StackDockStation**, this station consists of four layers. Layers 1, 3 and 4 are identical to the layers of the **StackDockStation**. A background panel (1), **DockableDisplayers** (3) to paint decorations and the children (4). Layer 2 is the logical tree which tells how to lay out the children. The nodes of this tree consist of **SplitNodes** and the root can be accessed through the method **getRoot**. Clients should never add or remove nodes from the tree directly.



2.3.3 FlapDockStation


This station is a list of buttons. If the user clicks on one of the buttons a window opens showing a child. Only one child can be shown at a time. This station can be used as sidebar to collect “minimized” **Dockables**.



2.3.4 ScreenDockStation

The **ScreenDockStation** allows its children to float around freely on the screen. Each child is put onto its own window which is independent from any other window. This station also offers a “fullscreen mode” where a window is enlarged to fill the entire space of a screen.

This station is pretty simple and consists of only 3 layers. Some windows (1), instances of `ScreenDockWindow`, provide a container to show the children. On each window there is a `DockableDisplayer` (2) to paint decorations, and on top is one `Dockable` child (3).



2.4 DockController

A `DockController` holds `Dockables`, `DockStations` and other supporting elements together. Most tasks are not handled by the `DockController` but by one of its sub-controllers, e.g. drag and drop is handled by the `DockRelocator`.

There can be more than one `DockController` in an application. Each controller has its own realm and there is no interaction between controllers. But most applications will need only one `DockController`.

Clients need to register the roots of their `DockStation-Dockable`-trees. They can use the method `add` of `DockController` to do that. All children of the root will automatically be registered as well. If a `DockStation` is not registered anywhere, it just does not work properly. For `Dockables` one could say that registration equals visibility. A registered `Dockable` can be seen by the user, an unregistered not.



`DockController` uses other classes to handle tasks. Many of these classes can be observed by listeners. An incomplete list:

DockRegister: a list of all `Dockables` and `DockStations`.

DockRelocator: handles drag and drop operations, can create a `Remote` to play around without user interaction.

DoubleClickController: detects double clicks on `Dockables` or on components which represent `Dockables`.

KeyBoardController: detects `KeyEvents` on `Dockables` or on components which represent `Dockables`.



Never forget to register the root-`DockStation(s)` at the `DockController` using the method `add`.



Why not just one `DockController` implemented as singleton? A singleton would make many interfaces simpler, eliminating all the code where the controller is handed over to even the smallest object. But there is absolutely no reason why only one controller should exist. A controller has no unique property that would justify a singleton. And not using a singleton gives more flexibility.

2.5 DockFrontend

`DockController` only implements the basic functionality. While this allows developers to add new exciting shiny customized features, it certainly doesn't help those developers which just want to use the framework.

The class `DockFrontend` represents a layer before `DockController` and adds a set of helpful methods. Especially a “close”-button and the ability to store and load the layout are a great help. `DockFrontend` replaces `DockController`, clients should add the root-`DockStations` directly to the frontend, not to the controller. They can use the method `addRoot` to do so.



`DockFrontend` adds a few nice features but not enough to write an application without even bothering to have a look at `DockingFrames`. Developers which can live with not having absolute control over the framework should use `Common`. `Common` adds all those features which make a docking-framework complete, e.g. a “minimize”-button



`DockFrontend` was written long after `DockController`. For the most part it just reuses code that already exists. It would be possible to write two applications with exact the same behavior once with and once without `DockFrontend`. The only thing that `DockFrontend` adds to the framework is a central hub where all the important features are accessible and a good set of default-values for various properties of the framework.



Use the methods called `setDefault...` to set default values for properties which will be used for all `Dockables`, e.g. whether `Dockables` are hideable or not.

2.5.1 Close-Button

In order to show the close-button clients need first to register their `Dockables`. The method `addDockable` is used for that. Each `Dockable` needs a unique identifier that is used internally by `DockFrontend`. Later clients can call the method `setHideable` to show or to hide the close-button.

By calling the method `setShowHideAction` clients can make the buttons invisible for all `Dockables`, note however that the `Dockables` hideable-property is not affected by this method.

If clients want to control whether a `Dockable` can be closed, they should add a `VetoableDockFrontendListener` to the `DockFrontend`. This listener will be informed before a `Dockable` is made invisible and allows to cancel the operation.



Why is the close-button not part of the very core of the framework? For one because the very core works on abstract levels and should not be made more complex with special cases like this button. There are also different implementations of this button and not all perform the same actions when pressed (this is especially true when using `Common`).

2.5.2 Storing the layout

The methods `save`, `load`, `delete` and `getSettings` are an easy way to store and load the layout. This mechanism will be explained in detail in another chapter.

3 Load and Save layouts

The layout of an application consists of the location, size and relationship of all the **Dockables** and **DockStations**. **DockingFrames** offers methods to store this layout persistent. Applications should use persistent layouts because the user certainly does not want to set up his preferred layout everytime when the application restarts.

DockingFrames distinguishes between local and global layout information:

1. Local information describes the relationship between one **Dockable** and its parent(s). Local information is represented by a chain of **DockableProperty**s, and each **DockStation** offers a method **getDockableProperty** to find the location of one of its children.
2. Global information describes the relationship of an entire tree of **Dockables** and **DockStations**. The class **DockSituation** offers methods to extract and to apply this data from a living.

It should be noted that applications need to handle both local and global information in order to create a truly persistent layout. Local information is needed to store the location of **Dockables** which are invisible (not in the tree), global information is needed when stopping and starting the application. There are no algorithms implemented to create global information out of local information, and there are only basic algorithms which create local information out of global information. In any case, conversion between these two formats should be considered not to be possible.

Algorithms to handle layout information are offered by the **DockFrontend** (see 3.5). For many applications the easiest solution for persistent layouts is to use a **DockFrontend**, and completely ignore all the other sections of this chapter.

3.1 Placeholders

Placeholders are an optional extension that allow clients to link global and local information. The idea behind placeholders is, that some **Dockables** can be assigned a unique identifier. If such a **Dockable** is removed from a **DockStation**, then a placeholder remains. At later time when the **Dockable** is added again to that station, the placeholder can be used to place the element at its former location. Placeholders are stored in the global and the local layout information, and thus build a link.

In **Core** this mechanism is normally disabled. Clients must implement a new **PlaceholderStrategy** and install the strategy using the property key **PlaceholderStrategy.PLACEHOLDER_STRATEGY**. The strategy should be set up before reading a layout, otherwise all placeholders will be marked as invalid and be deleted. The strategy should also be applied to any **DockSituation** that is created by clients.



Placeholders were introduced in version 1.0.8. One of the reasons they were not used earlier is that they make data structures complex. Also detecting and removing invalid and outdated placeholders requires some work.



Most `DockStations` use the `PlaceholderList` and the `PlaceholderMap` to manage their `Dockables` and placeholders.

3.2 Local: `DockableProperty`

Every `DockStation` can create `DockableProperty`-objects for its children. Each of these `DockableProperty`s contains the position, size, placeholder and/or other data about one child.

Some `DockStations` are also `Dockables`. Those stations are not only able to create `DockableProperties` for their children but their parents can create a property for them. These two properties can be strung together to form a chain describing the position of a grand-child on its grand-parent.

3.2.1 Creation

How to create a `DockableProperty`? One way is of course just to create new objects using `new XYProperty(...)`. The other way is to retrieve them from some `DockStations` and `Dockables`:

```
1 Dockable dockable = ...
2
3 DockStation root = DockUtilities.getRoot( dockable );
4 DockableProperty location = DockUtilities.getPropertyChain( root ,
    dockable );
```

In line 1 we get some unknown `Dockable`. In line 3 the `DockStation` which is at the top of the tree of stations and `Dockables` is searched. Then in line 4 the location of `dockable` in respect to `root` is determined.

There are seven **DockableProperties** present in the framework.

StackDockProperty for **StackDockStation**, contains just the index of the **Dockable** in the stack.

FlapDockProperty for **FlapDockStation**, contains index, size and whether the **Dockable** should hold its position when not focused.

ScreenDockProperty for **ScreenDockStation**, contains the boundaries of a **Dockable** on the screen.



SplitDockProperty for **SplitDockStation**. This deprecated property contains the boundaries of a **Dockable** on the station.

SplitDockPathProperty also for **SplitDockStation**. This new property contains the exact path leading to a **Dockable** in the tree that is used internally by the **SplitDockStation**.

SplitDockPlaceholderProperty also for **SplitDockStation**. This property stores a placeholder, an identifier whose position is already known to the **SplitDockStation**. If the placeholder is not found, then a backup property can be applied.

SplitDockFullScreenProperty also for **SplitDockStation**. This property points to a child that is maximized.

3.2.2 Usage

How to apply a **DockableProperty**? Every **DockStation** has a method **drop** that takes a **Dockable** and its position. That might look like this:

```
1 Dockable dockable = ...
2 DockStation root = ...
3 DockableProperty location = ...
4
5 if( !root.drop( dockable, location ) ){
6     root.drop( dockable );
7 }
```

In lines 1-3 some elements that were stored earlier are described. In line 5 we try to drop **dockable** on **root**, if that fails we just drop it somewhere (line 6).

DockablePropertys are not safe to use. If the tree of stations and **Dockables** changes, then an earlier created **DockableProperty** might not be consistent anymore. The method **drop** of **DockStation** checks for consistency and returns **false** if a **DockableProperty** is no longer valid.



Always check the result of **drop**, if it is **false** then the operation was canceled by the station because the property is invalid.

3.2.3 Storage

`DockableProperty`s can be stored either as byte-stream or in xml-format by a `PropertyTransformer`. A set of `DockablePropertyFactories` is used by the transformer to store and load properties. The factories for the default properties are always installed. If a developer adds new properties then he should use the method `addFactory` to install new factories for them.



If using `DockFrontend` the method `registerFactory` can be used to add a new `DockablePropertyFactory`. This factory will then be used by the global transformer of the frontend.

3.3 Global: `DockSituation`

The layout of a whole set of `Dockables` and `DockStations` can be stored with the help of a `DockSituation`. A `DockSituation` is a set of algorithms that transform the layout information from one format into another, e.g. from the dock-tree (built by stations and `Dockables`) to an xml-file. A `DockSituation` uses various factories for these transformations.

3.3.1 Basic Algorithms

Global layout information appears in five formats:

dock-tree format The set of `Dockables` and `DockStations` as they are seen by the user.

binary format A file containing binary data. This file is normally written by a `DataOutputStream` and read by a `DataInputStream`.

xml format A file containing xml. To write and read such a file the class `XIO` is used.

layout-composition format An intermediate format that consists of a set of `DockLayoutCompositions`. These objects are organized in a tree that has the same form as the dock-tree.

perspective format A lightweight version of the “dock-tree format”, for easy modification by clients. More about perspectives can be found in section 3.4.

If converting from `a` to `b` then a `DockSituation` will always first convert `a` to `layout-composition` and then `layout-composition` to `b`.



`DockSituation` always creates new files or new objects. In its basic form it is not able to reuse existing elements.

A `DockSituation` uses different factories and strategies for these conversions:

DockFactory These factories are responsible to load or store the layout of a single **Dockable** or **DockStation**. Like **DockSituation** they need to support four formats. For one the dock-element they store or read, then binary- and xml-format and finally some object as intermediate format. They are free to choose any kind of object as intermediate format.

AdjacentDockFactory They function the same way as **DockFactories** but can be used for arbitrary dock-elements. **AdjacentDockFactories** are used to store additional information about elements, that can, but does not have to be, layout information.

MissingDockFactory These are used when another factory is missing. The **MissingDockFactory** can try to read the xml-format or binary-format and convert it to the intermediate format.

DockSituationIgnore This strategy allows a **DockSituation** to ignore dock-elements when storing the layout. That can be helpful if for example an application has **Dockables** which show only temporary information that will be lost on shutdown anyway.

PlaceholderStrategy This strategy filters placeholders, invalid placeholders are removed from the layout.

A **DockSituation** can handle missing factories when reading xml or binary format. It first tries to use a **MissingDockFactory** to read the data, if that fails it either throws away the data (for **AdjacentDockFactories**) or stores the data in the layout-composition as “bubble” in its raw format. These “bubbles” can be converted later when the missing factories are found.



A **DockLayoutComposition** contains a lot of information. First of all a list of children to build the tree. Then a list of **DockLayouts** which represent the information from **AdjacentDockFactories**. Each **DockLayout** contains a unique identifier for the factory and the data generated by the factory. Finally a **DockLayoutComposition** contains a **DockLayoutInfo** which represents the data of or for a **DockFactory**. A **DockLayoutInfo** either contains a **DockLayout** (the normal case) or some data in xml or binary format. The later case happens if a factory was missing while reading a file, the information gets stored until it can be read later.



The method **fillMissing** can be used to read “bubbles” in raw format. The method **estimateLocations** can be used to build **DockablePropertyts** for the elements. These are the positions were the elements would come to rest if the layout information were converted into a dock-tree.

3.3.2 Basic Usage

How is a `DockSituation` utilized in order to load or store the layout of an application?

Each `Dockable` and each `DockStation` has a method `getFactoryID`. This method returns an identifier that has to match the unique identifier that is returned by the method `getID` of `DockFactory`. The first step in using a `DockSituation` will always be to make sure that for any identifier a matching `DockFactory` is available. Clients have to call the method `add` of `DockSituation` to do so.



Default factories are installed for `DefaultDockable`, `SplitDockStation`, `StackDockStation` and `FlapDockStation`.



The `ScreenDockStationFactory` for `ScreenDockStation` is not installed per default. This factory requires a `WindowProvider` to create the station, and since this provider cannot be guessed by `DockSituation` the factory is missing. Clients have to add `ScreenDockStationFactory` manually.

Afterwards clients just have to call `write` or `writeXML` to write a set of `DockStations` and their children. Clients can later call `read` or `readXML` to read the same map of elements. Note that every call to `read` or `readXML` will create a new set of `Dockable`- and `DockStation`-objects.

Let's give an example how to write an xml file:

```
1  try{
2      JFrame frame = ...
3      DockStation root = ...
4
5      DockSituation situation = new DockSituation();
6      situation.add( new ScreenDockStationFactory( frame ) );
7      situation.add( new MySpecialFactory() );
8
9      Map<String, DockStation> map = new HashMap<String, DockStation>();
10     map.put( "root", root );
11
12     XElement xlayout = new XElement( "layout" );
13     situation.writeXML( map, xlayout );
14
15     FileOutputStream out = new FileOutputStream( "layout.xml" );
16     XIO.writeUTF( xlayout, out );
17     out.close();
18 }
19 catch( IOException ex ){
20     ex.printStackTrace();
21 }
```

On line 2 the main-frame of the application is given and on line 3 the applications root `DockStation`. The first step is to create a new `DockSituation` on line 5 and add the missing `ScreenDockStationFactory` on line 6. Then other factories that are not part of `DockingFrames` but the application itself can be added like on line 7. On lines 9, 10 a map with all the root-stations of the application is built up. Then on line 12 we prepare for writing in xml-format by creating

a `XElement`. The situation converts the dock-tree to xml-format in line 13. Finally on lines 15-17 the xml-tree is written into a file “layout.xml”.

The next example shows how reading from binary format can look like:

```

1  try{
2      JFrame frame = ...
3
4      DockSituation situation = new DockSituation();
5      situation.add( new ScreenDockStationFactory( frame ) );
6      situation.add( new MySpecialFactory() );
7
8      FileInputStream fileStream = new FileInputStream( "layout" );
9      DataInputStream in = new DataInputStream( fileStream );
10
11     Map<String, DockStation> map = situation.read( in );
12
13     in.close();
14
15     SplitDockStation station = (SplitDockStation)map.get( "root" );
16     frame.add( station.getComponent() );
17 }
18 catch( IOException ex ){
19     ex.printStackTrace();
20 }

```

What happens here? In line 2 the main frame of the application is defined. In lines 4-6 a `DockSituation` is set up. In lines 8, 9 a file is opened. In line 11 that file gets read by the `DockSituation` and a map that was earlier given to `write` is returned. In line 15 the fact that `map` was earlier given to `write` is used to guess that there is a `SplitDockStation` with key “root” in the map. Finally in line 16 that station is put onto the main-frame which now shows the new elements.

3.3.3 Reuse existing Dockables

The major drawback of the basic algorithms is that they always create new `Dockables` and `DockStations`. It is nearly impossible to just change the layout while an application is running, a layout can only be loaded on startup. `PredefinedDockSituation` builds upon `DockSituation` and extends the algorithms in a way that they can reuse existing dock-elements.

The extended algorithm uses a special `DockFactory`, called `PreloadFactory`, that is wrapped around the factories provided by the client. Writing does not change much, the `PreloadFactory` delegates the work just to the original `DockFactory`. Reading however is more interesting, the `PreloadFactory` forwards an already existing dock-element to the the original `DockFactory` which then updates the layout of the element.

A side effect of this implementation is that for the basic algorithms no factory seems ever to be missing. In fact the issue of missing factories is just moved to the `PreloadFactory`. The `PreloadFactory` can however store data in its raw format if necessary.



A `PreloadFactory` uses a `PreloadedLayout` as intermediate format. This `PreloadedLayout` contains the unique identifier of the original `DockFactory` and a `DockLayoutInfo`. The `DockLayoutInfo` contains either data in raw format or in the intermediate format of the original factory.

What happens if a `PredefinedDockSituation` finds layout information for an element, has all the necessary factories but not the element itself? The default behavior is to ignore the information. However it is possible to use backup-DockFactories. These backup factories will create new elements if the originals are missing. They are also used when reading raw format and the original factory is missing. These backup factories are added through `addBackup`, they have to use a `BackupFactoryData` as intermediate format.



Note that the `MissingDockFactory` of `DockSituation` is not used for elements that were predefined on writing, because for those elements the `PreloadFactory` - which is never missing - was used.



The existence of these two sets of algorithms, basic and extended, lays in the history of `DockingFrames`. First the basic algorithms were written. They did their job well for small applications. But when applications began to grow it became evident that their were not sufficient. Instead of rewriting them another layer was added. The division in two sets of algorithms has also the advantage of reduced complexity.

`PredefinedDockSituation` is used in the same way as `DockSituation`. The only difference is the possibility to predefined elements. The method `put` can be used for that. This method expects a unique identifier for any new element.

An example can look like this:

```

1   DockStation rootStation = ...
2   Dockable fileTreeDockable = ...
3   Dockable contentDockable = ...
4
5   PredefinedDockSituation situation = new PredefinedDockSituation();
6
7   // setup situation {...}
8
9   situation.put( "root", rootStation );
10  situation.put( "file-tree", fileTreeDockable );
11  situation.put( "content", contentDockable );
12
13  // read or write {...}

```

In lines 1-3 some `DockStations` and `Dockables` are defined. These are the elements that are always present and need not to be recreated when loading a layout. In line 5 a new `PredefinedDockSituation` is created. Then the basic setup (adding factories, ...) is done in line 7. In the lines 9-11 the predefined elements are added to the situation. For each of them a unique identifier is choosen. Finally in line 13 we can either write or read the layout.



Any `String` can be used as unique identifier. Small identifiers with no special characters are however much less likely to attract any kind of trouble.

3.3.4 Extract local information

It is possible to extract `DockableProperty`s from a global layout with the help of a `DockSituation`. First the layout data is required in its intermediate format. This data can only be accessed if the client uses its own format to store layout data. As an example, storing the layout of one `DockStation` using XML:

```
1 public void write( StackDockStation station, DockSituation situation,
2   XElement out ){
3   DockLayoutComposition intermediate = situation.convert(station);
4   situation.writeCompositionXML(intermediate, out.addElement("layout")
5   );
6 }
```

Once the client has acquired the data in its intermediate format it can use `estimateLocations` to assign locations to each node in the tree of compositions. An example using XML:

```
1 public void read( DockSituation situation, XElement in ){
2   // acquire intermediate data
3   DockLayoutComposition intermediate = situation.readCompositionXML(in
4   .getElement("layout"));
5
6   // guess locations
7   situation.estimateLocations(intermediate);
8
9   // get the location of the root (which will be null, because the
10  // root has no parent)
11  DockableProperty location = intermediate.getLayout().getLocation();
12 }
```

It is up to the client to find out which `DockLayoutComposition` represents which `Dockable`. A custom `DockFactory` can help by storing some keys in the layout which can later be identified by the client.



A `DockFrontend` will estimate locations of those missing `Dockables` for which `addEmpty` was called.



If using a `PredefinedDockSituation`, the method `listEstimatedLocations` is of interest as it returns a map of identifier-location pairs. The identifiers are the identifiers of the `Dockables` which were added by the client to the situation.

3.4 Perspectives

Layout information appears in different formats, perspectives is one of these formats. Perspectives offer clients a way to read, modify or build layout information using lightweight objects and keeping typesafety.

In order to work with perspectives clients need access to a `Perspective` object:

- Any `DockSituation` offers a method `createPerspective` which sets up a new `Perspective` using the current settings of the `DockSituation`.
- `DockFrontend` offers a method `getPerspective`. Clients can provide a `FrontendPerspectiveCache` which basically converts `Dockables` and

`DockStations` to their counterparts in the perspective API. This is required for clients that introduce their own `DockFactory`s.



The `FrontendPerspectiveCache` allows clients to use their own, specialized classes to describe `Dockables` and `DockStations`. This may not be necessary for all clients, these clients can make use of the `DefaultFrontendPerspectiveCache`.

Once a `Perspective` object is acquired it can be used to directly read and write the xml, binary or the intermediate format. Clients using a `DockSituation` should use the `convert` methods to create or apply the intermediate format. Clients using a `DockFrontend` should use the `get/setSetting` methods in order to access and apply layouts through the intermediate format.

`Perspective` creates objects of type `PerspectiveElement`. There are various subtypes of this interface, in fact for each type of `Dockable` or `DockStation` of the framework there is a subtype representing exactly that item (e.g. `SplitDockPerspective` represents `SplitDockStation`). Clients are free to move around elements in any way they wish. However, the perspective API does not enforce the correctness of the layout, it is the clients responsibility to build a layout that actually makes sense.

3.5 DockFrontend

`DockFrontend` offers storage for local and for global layout information. Clients need to register their `Dockables` through `addDockable` if they want access to the full range of storage-features.

Layout information can be stored in xml- or binary-format. The methods `write`, `writeXML`, `read` and `readXML` will take care of this.

3.5.1 Local

Whenever `hide` is called for a registered `Dockable` its local position gets stored. If later `show` is called this position is reapplied and the element shows up at the same (or nearly the same) location it was earlier.

3.5.2 Global

`DockFrontend` internally uses a `PredefinedDockSituation` to store the global layout. All root-`DockStations` and all registered `Dockables` are automatically added to this situation. The global layout can either be stored on disk or it can be stored in memory. It is possible to store more than just one layout in memory and allow the user to choose from different layouts. There are methods to interact with the layouts in memory:

save Saves the current layout in memory. Clients can provide a name for the layout or use the name of the last loaded layout.

load Loads a layout. The name of the layout is used as key.

delete Deletes a layout from memory.

getSettings Gets a set of names for the different layouts.

getCurrentSetting Gets the name of the layout that is currently loaded, can be null.

setCurrentSetting If there is a layout with the name given to this method than that layout is loaded. Otherwise the current layout gets saved with the new name.

3.5.3 Missing Dockables

The default behavior of **DockFrontend** is to throw away information for missing **Dockables**. It is however possible to change that behavior.

If data needs to be stored for a missing **Dockable** then **DockFrontend** uses an “empty entry”. Clients can define new empty entries by invoking the method **addEmpty**. Existing entries can be removed with **removeEmpty**, with **listEmpty** all empty entries can be accessed. Once an entry has been marked as “empty” it can switch between filled and empty as many times as necessary without losing its layout information. The **DockFrontend** can even store data in raw xml or binary format and convert this data later once an appropriate **DockFactory** becomes known.



“Empty entries” are best to be used if a client already knows the identifiers of all the **Dockables** that can eventually be registered at the **DockFrontend**.

Another way is to register backup-**DockFactories** by calling the method **registerBackupFactory**. These factories will create new **Dockables** which are then automatically registered.



A backup-factory is the strongest weapon against missing information. If there is a possibility to use them, use them.

And finally there is the **MissingDockableStrategy** which can be set using **setMissingDockableStrategy**. This strategy enables or disables to automatic processes.

- It allows to create “empty entries” automatically. There are two methods **shouldStoreShown** and **shouldStoreHidden** which have to check the identifiers and to return **true** to allow a new empty entry.
- It allows to use new **DockFactories** as soon as they become known. Normally **DockFrontend** does not change the layout without the explicit command from a client (by invoking **setSetting** directly or indirectly). If **shouldCreate** returns **true** however **DockFrontend** will update the layout as soon as enough information is available to do so.



`MissingDockableStrategy` should be used when no information about what is missing is available. It allows to run a “do whatever is possible”-strategy.



If a strategy allows to store anything and a client often uses different identifiers for their `Dockables`, then layouts will start to grow and never stop. Don't forget to delete outdated information.



The interface `MissingDockableStragey` offers two default implementations: `DISCARD_ALL` and `STORE_ALL`. The first implementation is set as default and allows nothing, the second one allows everything.

4 Actions

All **Dockables** can be associated with some actions. An action normally appears as some kind of button in the title of a **Dockable**, they can however appear at other places as well. There are different types of actions, some may behave like a **JButton** others like a **JCheckBox**, clients can add new types.




Figure 1: A **Dockable** with a few **DockActions** in its title and on a popup menu. The action marked by an arrow is the same object just shown in different views.

Actions are represented by the interface **DockAction**. Each **Dockable** has a list of them represented by a **DockActionSource**.

If some component wants to show some actions it firsts asks a **Dockable** for its global **DockActionSource**. It then asks each **DockAction** of that list to create a view that fits to the component. A title will ask for another kind of view than a menu. At any time actions can be added or removed from the **DockActionSource** and any component showing actions will react on these events.



The interface **DockAction** is quite simple. Two methods to install (**bind**) and to uninstall (**unbind**) the action. One method to create new views (**createView**) and one method to trigger an action programmatically (**trigger**). More useful are the many subclasses and subinterfaces. **StandardDockAction** introduces icons, text and tooltip. Five subinterfaces for **StandardDockAction** exist and for all of them a default-view is provided.



There are three levels in the design of **DockAction** and its subclasses. First there is **DockAction** which allows almost any kind of **Component** to be used as view. Second there are subinterfaces for the standard tasks, the framework provides views for them. Third are real implementations of the second-level interfaces. Some interfaces are implemented in more than one action for different styles of application organization.

4.1 Show Actions

Assuming one has a `DockAction` (more about different kind of actions is in the next chapter) how can the framework be advised to show it?

4.1.1 List of Actions

`DockActions` never travel alone in this framework. They always travel with other actions in a `DockActionSource`. Actions can be added or removed from `DockActionSources` at any time and modules showing actions will react on this.

Most methods of `DockActionSource` can be understood without explanation. The method `getLocationHint` is an exception. It returns a `LocationHint` which is used to order several `DockActionSources` into a list (and treat them as one big `DockActionSource`). Clients which implement an `ActionOffer` can also introduce new kind of `LocationHints`.



`LocationHints` consists of an `Origin` and a `Hint`. The hint tells the preferred location in respect to other elements, the origin are used if multiple hints collide. New `Hints` and `Origins` can be written.

4.1.2 Source of Actions

Actions have different sources, each kind of source has a specific purpose.

- The **local action source** is part of every `Dockable`. This source is accessed through `getLocalActionOffers`. If `AbstractDockable` or a subclass like `DefaultDockable` is used then `setLocalActionOffers` allows to quickly set and exchange the actions. This source of actions should be used for actions that are closely linked with some `Dockable`.
- `ActionGuards` can add actions to every `Dockable`. An `ActionGuard` is added to a `DockController` through `addActionGuard`. Its method `react` will be called whenever the actions of a `Dockable` are searched. If `react` returns `true` then the method `getSource` is called. This source of actions is intended for general purpose actions and for actions which need a special position in the list of actions (e.g. a close-action needs to be at the very end).
- Every `DockStation` can add **direct** and **indirect action offers** to its children. For this `DockStation` has two methods `getDirectActionOffers` and `getIndirectActionOffers`. **Direct action offers** are used only for true children, **indirect action offers** can be applied to grandchildren as well. These sources of actions are intended for actions that are linked to a `DockStation`, like the `maximize-action` that can be seen on a `SplitDockStation`.

Two mechanisms are responsible for collecting all the actions from these different sources and to put them into a list. Clients can adjust these mechanisms even to a point where they no longer collect actions but introduce their own actions.

- Every `DockController` has at least one `ActionOffer`. An `ActionOffer` has two methods: `interested` tells whether the offer is interested in managing a certain `Dockable` and `getSource` collects the actions of an interesting `Dockable`. The primary function of an `ActionOffer` is to order the various sources. It is up to the offer to decide how to actually do the sorting. The default `ActionOffer` uses the `LocationHint` which is attached to every `DockActionSource`.

Clients can use `addActionOffer` and `setDefaultActionOffer` to change the offers of a `DockController`. The public method `listOffers` then advises the controller to use one of its offers.

- Modules which need a list of actions call `getGlobalActionOffers` from `Dockable`. This method is the ultimate piece of code which decides what to show. This method can ignore anything else that has been said in this chapter and introduce its very own mechanism to collect actions.

Most `Dockables` will utilize `HierarchyDockActionSource` instead of implementing `getGlobalActionOffers`. This special source observes the hierarchy of a `Dockable` and changes its content automatically. `Dockables` using `HierarchyDockActionSource` should `bind` the source. They need to call `update` if their own local action source is exchanged.



It is generally a bad idea to write `DockActionOffers` or `getGlobalActionOffer` methods which do not just collect actions. There are already mechanisms to introduce `DockActions` and they should suffice for every possible situation.

4.2 Standard Actions

There are a number of standard actions in the framework. Clients can either subclass them or instantiate and add listeners to them. A user would put the actions into six groups:

Button If the user clicks this action then always the same thing happens. The interface `ButtonDockAction` collects all the buttonlike actions.

Checkbox When triggered it changes some property from `true` to `false` or from `false` to `true`. All actions with this behavior implement the interface `SelectableDockAction`.

Radiobutton Like a group of checkboxes, but only one radiobutton can be selected within that group. Like checkboxes all these actions are represented by `SelectableDockAction`. Several radiobuttons can be linked together with the help of a `SelectableDockActionGroup`.

Menu A menu just contains a list of other `DockActions`. These other actions are normally hidden and only shown if the user wants to see them. Menus are implementing the interface `MenuDockAction`.

Drop-down-button Like a menu but the last triggered action can be triggered again without opening the menu. The interface `DropDownAction` represents these special menus.

Separator A separator just is a line, a graphical element to divide a set of actions into subsets. Separators are implemented through the class `SeparatorAction`.

4.2.1 Simple actions

Simple actions are a set of classes that implement the various action-interfaces. These simple actions do not have any advanced features and should be quite simple to use. An example might be the following code:

```
1 public class ExampleAction extends SimpleButtonAction{
2     public ExampleAction() {
3         setText( "Run..." );
4         setIcon( new ImageIcon( "example.png" ) );
5         setTooltip( "Run the example" );
6     }
7
8     @Override
9     public void action( Dockable dockable ) {
10         System.out.println( "kabum" );
11     }
12 }
```

Here the class `SimpleButtonAction` is used. The action is subclassed by `ExampleAction`. In lines 3-5 properties like the icon are set. The subclass overrides the method `action` (lines 9-11) which is invoked every time when the user presses the button.

The available simple actions are:

- **SimpleButtonAction**: For creating buttons. Can either be subclassed (like in the example above) or just instantiated. Clients can add instances of the well known `ActionListeners` which will be invoked when the user presses the button. Exactly like a `JButton`.
- **SimpleSelectableAction.Check** and **SimpleSelectableAction.Radio**: For creating checkboxes and radiobuttons. Clients can add instances of `SelectableDockActionListener` to be informed whenever the state of the action changes. A `SelectableDockActionGroup` can be used to make sure that only one action out of a set of actions is selected at any time.
- **SimpleMenuAction**: For creating menus. The method `setMenu` takes a `DockActionSource` and the content of this source will be shown.
- **SimpleDropDownAction**: For creating drop down menus. Has methods to get and set the selection, and methods to add or remove actions from the menu.

4.2.2 Group actions

Group actions are `DockActions` that can be used for many `Dockables` at once even with different properties for each `Dockable`. To be more precise, a `GroupKeyGenerator` will assign a key to each `Dockable`. If any view asks the action for a property (like the icon) this key will be used to search the property in a map. All the group actions extend the class `GroupedDockAction`.

Let's have a look at an example. The following action behaves like a checkbox. Its unique feature is the text that changes if the selected-state changes.


```

1  import bibliothek.gui.Dockable;
2  import bibliothek.gui.dock.action.actions.GroupKeyGenerator;
3  import bibliothek.gui.dock.action.actions.GroupedSelectableDockAction;
4
5  public class ExampleGroupAction extends
6      GroupedSelectableDockAction.Check<Boolean> {
7      public ExampleGroupAction() {
8          super( new GroupKeyGenerator<Boolean>(){
9              public Boolean generateKey( Dockable dockable ){
10                  return dockable.<getSomeProperty()>;
11              }
12          });
13          setRemoveEmptyGroups( false );
14
15          setSelected( Boolean.FALSE, false );
16          setSelected( Boolean.TRUE, true );
17
18          setText( Boolean.FALSE, "Unselected" );
19          setText( Boolean.TRUE, "Selected" );
20      }
21
22      @Override
23      public boolean trigger( Dockable dockable ) {
24          setSelected( dockable, !isSelected( dockable ) );
25          return true;
26      }
27
28      @Override
29      public void setSelected( Dockable dockable, boolean selected ){
30          dockable.<setSomeProperty( selected )>;
31          setGroup( selected, dockable );
32      }
33 }

```

The constructor (lines 7–20) sets up the action. First the `GroupKeyGenerator` is set in lines 9–12. The key is a `Boolean` which represents “some property” of a `Dockable`. The meaning of the property is not important. Through the keys `Dockables` get grouped. When `Dockables` get added and removed a group may become empty. Line 13 ensures that the action does not delete the properties of empty groups.

A `Boolean` only has two states, both states will be used as key. So there is a “true” and a “false” group. The selected-state of the action should match the key of the group. In other words: if “some property” is `true` then the action is selected, if “some property” is `false` then it is not. Lines 15, 16 are responsible for this setting. The same behavior is enforced for the text of the action in lines 18, 19.

The standard behavior of a `SelectableDockAction` is to change its selected state as soon as the user triggers the action. If the action is used for many `Dockables` than this behavior would look rather odd. All the actions would change their state and most of them would do so wrongly. By overriding the method `trigger` this problem can be prevented (lines 23–26). Instead of changing the selected state of the action, the group of the `Dockable` is changed by invoking `setSelected` in line 24. Since the two groups have different selection states the user will think that the action changed the state.

By the way: the method `setSelected` in lines 29–32 needs to be overridden since the default behavior is to change the state of the action, not to change the group of a `Dockable`.



Be careful when using group actions: they are complex to handle. In many cases a simple action can replace a group action.



Group actions were introduced for `DockStations`. `DockStations` need to apply the same actions to many `Dockables`. Instead of setting up new actions all the time it was easier to have one action that holds many properties at the same time.

There are only three group actions implemented:



- `GroupedButtonDockAction`
- `GroupedSelectableDockAction.Check`
- `GroupedSelectableDockAction.Radio`

4.3 Custom actions

Clients are free to implement new actions.

4.3.1 Reuse existing view

Whenever possible an existing view should be reused. There are 6 kind of views defined in the framework. Each kind of view is represented through an instance of `ActionType`, each of them is stored as constant in `ActionType` itself. `ActionType` has one generic parameter. The view can force an action to implement some interface through that parameter. For example, the kind `ActionType.BUTTON` forces an action to implement `ButtonDockAction`. Actions can use an `ActionType` as key for a factory that is stored in the `ActionViewConverter`.

An example for an action that uses an `ActionType` to create its view:

```

1 public class ExampleButtonAction implements ButtonDockAction{
2
3     public <V> V createView( ViewTarget<V> target ,
4                             ActionViewConverter converter, Dockable dockable ){
5
6         return converter.createView( ActionType.BUTTON, this ,
7                                     target , dockable );
8     }
9
10    public void action( Dockable dockable ){
11        [...]
12    }
13
14    public Icon getIcon( Dockable dockable ){
15        return [...];
16    }
17
18    [...]
19 }
```

Really important are the lines 3-8: these lines are all that is necessary to create different button-views for different environments (menu, title). The `ActionViewConverter` does all the work, it just has to be called with the correct parameters.

The interface `ButtonDockAction` declares other methods like `getIcon` (lines 14-16) which will not be a challenge to implement.

4.3.2 Custom view

Writing a custom action with custom view is possible, but will require a lot of work. Some good news: it is only necessary to implement the interface `DockAction` and the raw interface `DockAction` has only very few methods. The greatest challenge will be to write the method `createView`. This method can be called any time and receives a `ViewTarget`, a `ActionViewConverter` and the `Dockable` for which the view will be used. It has to return either `null` or the type of object that is specified as the generic parameter of `ViewTarget`. The framework will always use the same three instances of `ViewTarget`, all of them are stored as constants in `ViewTarget` itself. So in theory a `createView` could check which of the three `ViewTargets` it received and create one of three different views. In practice it is much better to use the `ActionViewConverter` for this task.

You might remember that the `ActionViewConverter` can instantiate new views if an `ActionType` is given to its `createView` method. So the first step should be to introduce a new `ActionType`. Only the second step is to write the new action-class. This could result in something like this:

```

1  import bibliothek.gui.Dockable;
2  import bibliothek.gui.dock.action.ActionType;
3  import bibliothek.gui.dock.action.DockAction;
4  import bibliothek.gui.dock.action.view.ActionViewConverter;
5  import bibliothek.gui.dock.action.view.ViewTarget;
6
7  public class CustomAction implements DockAction{
8      public static final ActionType<CustomAction> CUSTOM =
9          new ActionType<CustomAction>( "custom" );
10
11      public <V> V createView( ViewTarget<V> target ,
12                             ActionViewConverter converter , Dockable dockable ){
13          return converter.createView( CUSTOM, this ,
14                                     target , dockable );
15      }
16
17      @Override
18      public void bind( Dockable dockable ){
19          // ignore
20      }
21
22      @Override
23      public void unbind( Dockable dockable ){
24          // ignore
25      }
26
27      public boolean trigger( Dockable dockable ){
28          return false;
29      }
30 }

```

Now the `ActionViewConverter` needs to be instructed of what to do with the `ActionType` `CUSTOM`. This should be done on startup, before the first `CustomAction` is even created. The `ActionViewConverter` is accessible through

the `DockController`. A client can call `putDefault` to set the default view factory for some type and target:

```
1 DockController controller = ...;
2 ActionViewConverter converter = controller.getActionViewConverter();
3
4 ViewGenerator<CustomAction, BasicTitleViewItem<JComponent>> generator =
5     new CustomButtonGenerator();
6
7 converter.putDefault( CustomAction.CUSTOM, ViewTarget.TITLE,
8     generator );
```

In this code the converter is accessed in line 2. Some new factory is created in lines 4, 5 and this new factory is registered at the converter in lines 7, 8. The `CustomButtonGenerator` is just a class that implements `ViewGenerator`:

```
1 public class CustomButtonGenerator implements
2     ViewGenerator<CustomAction, BasicTitleViewItem<JComponent>>{
3     public BasicTitleViewItem<JComponent> create(
4         ActionViewConverter converter, CustomAction action,
5         Dockable dockable ){
6
7         return [...];
8     }
9 }
```



Set a `ViewGenerator` for `ViewTarget.TITLE`, `ViewTarget.MENU` and for `ViewTarget.DROP_DOWN`. Even if these generators do not create views but just return `null`, not installing them would lead to an error.

5 Titles

A `DockTitle` is a `Component` that may show an icon, a text, some `DockActions` or other information about a `Dockable`. Users often grab a `DockTitle` when they want to start a drag & drop operation.




Figure 2: Some `DockTitles`.

5.1 Lifecycle

Any client that wants to show a `DockTitle` needs to specify what *kind* of title it shows and needs to *request* a title.

The *kind* of a title is specified by a `DockTitleVersion`. New `DockTitleVersions` are obtained through the `DockTitleManager` (there is one per `DockController`). Creating a new `DockTitleVersion` requires the calling client to provide a default `DockTitleFactory`.

The *request* for a title is handled by a `DockTitleRequest`. Once a `DockTitleRequest` is created its method `request` can be called to execute the request. Clients should call `install` before using the request and `uninstall` once the request is no longer in use. This way the `DockTitleRequest` will automatically be executed again if the underlying `DockTitleFactory` is exchanged.

Once a `DockTitle` is acquired it must be connected with its `Dockable`. Clients must call the method `bind(DockTitle)` of `Dockable`, this tells the `Dockable` that it has a new title. If the client no longer shows the title it must call `unbind(DockTitle)`.



Do not call the method `bind` or `unbind` of `DockTitle`, these methods are called automatically by the `DockController`.

Dockables provide some information about their titles:



- The method `listBoundTitles` returns an list of all `DockTitles` which are currently in use for the `Dockable`.
- A `DockableListener` has several methods that will be invoked if titles get added, removed, updated or exchanged.

5.2 Custom titles

5.2.1 Implementing a new title

It is possible to replace all the titles in the framework. While the interface `DockTitle` is rather open, a title is responsible to collect all the information it wants to show by itself.

Most titles will have a constructor that has a `Dockable` as argument. They will add a `DockableListener` to their `Dockable` once `bind` is called and remove the listener once `unbind` is called.

There is only one connection between a module that shows a title and the title itself: the method `changed`. Modules use this method to send `DockTitleEvents` to the title.



A module does not need to know what title it shows. It just delivers the `DockTitleEvent` to the title. The module can use a subclass of `DockTitleEvent` to transfer more information than `DockTitleEvent` alone could carry. This design allows to use any implementation of `DockTitle` at any place while some titles still can use additional information from their environment. An example is the `EclipseDockTitleEvent` which is used by tabs. This event also tells the titles at which location they are and whether their tab is focused or not.

There are some classes that can help implementing a custom title:

- `AbstractDockTitle` provides standard implementations for most of the features a title requires. Subclasses only need to override the method `paintBackground` to have their custom painting code used.
- `BasicDockTitle` paints some gradients as background. Clients can change the color of these gradients. This title is also a good reference of how things can be done.
- `ButtonPanel` is a `Component` able to display a set of `DockActions`. `ButtonPanel` is able to show a popup-menu if there is not enough space for all actions.



In order to use the popup menu of `ButtonPanel` some special code has to be written. First: the argument `menu` of the constructor of `ButtonPanel` has to be set to `true`. Second: the method `getPreferredSize` of `ButtonPanel` cannot be used, any standard `LayoutManager` will fail. Instead the method `doLayout` of the `Container` which shows the panel can be overridden. In this `doLayout` method the container should call `getPreferredSize` to obtain a list of possible sizes of the panel. The n 'th dimension in this array tells how big the `ButtonPanel` would be if it would show n actions. The container should choose the biggest possible n and call `setVisibleActions`.

5.2.2 Apply the title

There are several ways to introduce a custom title into the framework.

To override or implement `requestDockTitle` of `Dockable` is the simplest way. The method just creates a new instance of the custom title when called.

Overriding or implementing `requestChildDockTitle` of `DockStation` allows to exchange the title of all children.

The `DockTheme` can be used as well. Either override the method `getTitleFactory` or call `setTitleFactory` when using a `BasicTheme`. With a few exceptions all the modules use the factory of the theme, hence replacing this factory will have a big effect.

Or use the `DockTitleManager` to make some better tuned settings. The `DockTitleManager` can be accessed by calling `getDockTitleManager` of `DockController`. Search the unique string identifier of the module that uses a title and call `getVersion` to access the associated `DockTitleVersion`. Then with the help of `setFactory` a new factory can be introduced. In code this could look like this:

```
1 DockController controller = ...
2
3 DockTitleManager manager = controller.getDockTitleManager();
4 DockTitleVersion version =
5     manager.getVersion( SplitDockStation.TITLE_ID, null );
6 version.setFactory( new CustomDockTitleFactory(), Priority.CLIENT );
```

6 Themes

A `DockTheme` relates to `DockingFrames` like a `LookAndFeel` to Java Swing. At any given time a `DockController` is associated with exactly one theme. The theme defines various graphical elements like icons, painting code and also some behavior. The current `DockTheme` can be changed through the method `setTheme`:

```
1 DockController controller = ...
2 DockTheme theme = new EclipseTheme();
3 controller.setTheme( theme );
```

6.1 Existing Themes

Several `DockThemes` are already included in the framework. A list of theme-factories can be accessed through the method `getThemes` of `DockUI`. This sub-chapter will list up the existing themes and mention some of their specialities.

Keep in mind that `DockThemes` do not have to follow a specific path for setting up their views. All the current themes are derived from `BasicTheme` and thus share a lot of concepts. Future or custom themes however might be implemented in different ways.

6.1.1 NoStackTheme

This theme is a wrapper around other themes. It prevents `StackDockStations` from having a `DockTitle` and makes sure that the user cannot drag or create a `StackDockStation` into another `StackDockStation`. The code for creating a `NoStackTheme` looks like this:

```
1 DockTheme original = ...
2 DockTheme theme = new NoStackTheme( original );
```

6.1.2 BasicTheme

The `BasicTheme` is a simple but working theme. All the other themes of the framework build upon `BasicTheme`. This theme shows content whenever possible. It tries to use all features and thus is quite good for debugging, to check whether all features are supported.




Figure 3: BasicTheme

6.1.3 SmoothTheme

SmoothTheme is basically the same as **BasicTheme**. The only difference is a replaced default **DockTitleFactory**. As a result new **DockTitles** are used by most elements, these new titles smoothly change their color when the “active” state of their **Dockables** changes.

6.1.4 FlatTheme

FlatTheme is a variation of **BasicTheme** that tries to minimize the number of borders. Among other things it uses new **DockTitles** and new views for **DockActions**. It is the ideal theme for developers that want to learn how to customize an existing theme.




Figure 4: FlatTheme

6.1.5 BubbleTheme

A more experimental theme. **BubbleTheme** often uses animations and other graphical gimmicks. It has a few performance issues, but it is a good theme to demonstrate the potential of the theme-mechanisms.




Figure 5: BubbleTheme

6.1.6 EclipseTheme

`EclipseTheme` tries to mimic the behavior and look of the well known IDE Eclipse. All the `Dockables` are shown on tabbed-components and often `DockTitles` are replaced by the tabs. The theme does not use the default theme-mechanisms as often as other themes and it might be a bit tricky to customize the theme. On the other hand it certainly looks good.




Figure 6: EclipseTheme

`EclipseTheme` offers some keys the map of properties that is stored in `DockProperties`. The keys are:

PAINT_ICONS_WHEN_DESELECTED A `Boolean` that tells whether icons on tabs should be painted if the tab is not selected. In every tabbed-component one tab has to be selected and its associated `Dockable` is the only visible element on the component.

THEME_CONNECTOR An `EclipseThemeConnector`. The connector tells whether a `DockAction` belongs onto a tab, or in a separate list of “unimportant” actions. The connector also tells what kind of title to use for a `Dockable`.

TAB_PAINTER A `TabPainter`. This class is a factory that creates the tab-components and sets up other settings that are related with tabs.



The `DefaultEclipseThemeConnector` puts every `DockAction` which is annotated with `EclipseTabDockAction` onto tabs.



The settings for titles and borders that are given by an `EclipseThemeConnector` are not respected if the element is on a `StackDockStations`. A `StackDockStation` always uses some tabbed-component.

6.2 Customize DockThemes

More than 50% of the frameworks source code is only used for painting stuff. No `DockTheme` uses particular complex code, just the mass can lead to some loss of direction. This sub-chapter will give only an overview of the basic classes, interfaces and concepts.



Many of the mechanisms used by `DockThemes` can be used by clients as well.

6.2.1 UI-Properties

UI-properties is a concept to distribute properties to components. A property could be a `Color` and a component some `DockTitle` which uses that color to paints it background. The basic idea is to use a map. The keys are `Strings`, the values are the properties. A `DockTheme` or a client can modify or put new key-value pairs into the map and components can read those values which are interesting for them.

Unfortunately a simple map is not enough. There needs to be a way to specify values that are used only by a subset of components. Or to remain with the map: the components must become part of the key as well.

The UI-properties provide the necessary features. The mechanism includes these classes, interfaces and generic parameters:

- **UIProperties:** the base map.
- **V:** the generic values that have to be distributed, e.g. the class `Color`.
- **UIValue:** A wrapper around `V`. Each component creates one `UIValue` for each query it will ask the `UIProperties`. In example a `DockTitle` would have to create and store exactly one `UIValue` to represent its background color. `UIValues` also act as observer and the `UIProperties` notify an `UIValue` if its wrapped `V` gets changed.
- **UIBridge:** An `UIBridge` is set between a set of `UIValues` and the `UIProperties`. `V` properties will not be handed directly from `UIProperties` to `UIValue` if there is a bridge between. The bridge can modify the `V` property in any way it likes, since the `UIBridge` knows the destination of a `V` it can also use information derived from the `UIValue`.

The implementation gets more complex:

- For each key several `V` properties can be put into the base map. Each value gets assigned another priority (“default”, “theme” or “client”) and only the one with the highest priority is used.
- Each `UIValue` is associated with a `Path`. The `Path` tells what an `UIValue` will do with the `V` property. The `Path` also tells what kind of type the `UIValue` has.

- **UIBridges** are also associated with a **Path**. An **UIBridge** is responsible to handle all those **UIValues** that are associated either with the same **Path** or a **Path** that has the bridges **Path** as prefix.



This scheme allows a flexible handling of resources. On one hand the number of keys is limited and one method call is enough to change a lot things in the user interface (e.g. all background colors of titles). On the other hand clients can implement sophisticated strategies to change some properties without the need to know in detail how the property will be used.

Originally this mechanism was invented to handle **Colors**. Then it became evident that the same mechanism could be used for other resources as well. The current implementation requires to implement several classes for each type of resource. While this might be annoying for the first use it ensures type safety. In a system where cause (writing in the map) and effect (reading from the map) can be separated by dozens of classes and an unknown amount of time one does not want to care about types as well.

6.2.2 Colors

In order to understand this chapter 6.2.1 should be read first.

All the colors used in the framework are handled by the **ColorManager**. The **ColorManager** is an **UIProperties** and can be accessed through the **DockController**. It's use could look like this:

```
1 DockController controller = ...
2 ColorManager colors = controller.getColors();
3 colors.put( Priority.CLIENT, "title.active.left", Color.GREEN );
```

In this snippet the value for the key “title.active.left” is changed to green. The priority **CLIENT** is highest possible priority. It is never overridden by the framework.

Or a more sophisticated use could involve a **ColorBridge**:

```
1 DockController controller = ...
2 ColorManager colors = controller.getColors();
3 colors.publish( Priority.CLIENT, TitleColor.KIND_TITLE_COLOR, new
4     ColorBridge(){
5         public void add( String id, DockColor uiValue ){
6             // ignore
7         }
8         public void remove( String id, DockColor uiValue ){
9             // ignore
10        }
11        public void set( String id, Color value, DockColor uiValue ){
12            TitleColor title = (TitleColor)uiValue;
13            if( title.getTitle().getDockable() == <somevalue> )
14                title.set( Color.GREEN );
15            else
16                title.set( value );
17        }
18    });
```

Here a **ColorBridge** for the **Path** **KIND_TITLE_COLOR** is installed in line 3. This path is only used by **UIValues** that implement **TitleColor**. Hence the unchecked cast from **DockColor** to **TitleColor** in line 11 is safe. The methods **add** (line 4-6) and **remove** (line 7-9) are called by **UIProperties** when a

`UIValue` gets added or removed to it. These methods can be ignored as long as the bridge does not change the color on its own. Otherwise the `DockColors` could be stored in some list and their method `set` could be called whenever the color needs to be exchanged.

This bridge searches for a specific `Dockable` called “somevalue” (line 12). The bridge returns `GREEN` for all colors used by any title of this `Dockable`. There is no distinction between the colors for background, foreground or other usages.



There is no global list of keys and every `DockTheme` uses different keys. All the modules that need colors are annotated with `ColorCodes` and expose their own list of keys to the API-documentation. Also the method `updateColors` of `BasicTheme` or subclasses can help: in this method all the colors that will ever be used by the theme are written into the `ColorManager`.



All the standard themes use a `ColorScheme` as their initial set of colors. All the standard themes provide a key for the `DockProperties` to change that initial scheme. For example the key provided by `BasicTheme` is stored as constant `BASIC.COLOR.SCHEME`. There are several subclasses of `ColorScheme` for the different themes.

By the way: some themes use colors that are read from the current `LookAndFeel`. Clients can call the method `registerColors` of `DockUI`. This method takes a `LookAndFeelColors` which is responsible in reading the colors from the `LookAndFeel`.

6.2.3 Fonts

Fonts use the same mechanism as Colors. A `FontManager` can be accessed through the methods `getFonts` of `DockController`. Unlike colors a set of standard keys are defined as constants in `DockFont`.

The `FontManager` does not distribute `Font`-objects but `FontModifiers`. A `FontModifier` has one method that receives the original `Font` and can return any `Font` it likes. In example a `FontModifier` could inverse the bold-property of a `Font`. There are two `FontModifiers` ready to use:

- `ConstantFontModifier` does not modify anything but always return the same `Font`
- `GenericFontModifier` can modify the italic-, bold- and size-property of a font.



Clients that want to use a `FontModifier` might be interested in the classes `DLabel` and `DPanel` which already modify their font. Also the class `FontUpdater` can be used to create new `JComponents` with the capability to modify their font.

6.2.4 Icons

Icons can be modified through the `IconManager`. The `IconManager` is just a map with the capability to inform observers if some of its value changed. The `IconManager` can be accessed through the method `getIcons` of `DockController`.

There is no global list of keys in the source code. However the file “icons.ini” contains a list of keys and paths of all the default icons.

6.2.5 Actions

The views for `DockActions` are changed through the `ActionViewConverter`. Please read chapter 4 for more information.

6.2.6 Titles

`DockTitles` are managed by the `DockTitleManager`. Please read chapter 5 for more information.

6.2.7 Displayers

A `DockableDisplayer` is a wrapper around a `Dockable` painting some decorations like a title or some border. All `DockStations` make use of `DockableDisplayers` to paint their children. `DockableDisplayers` are created by `DisplayerFactorys` which are provided by the current `DockTheme`.

Once a `DockableDisplayer` is created it cannot be replaced until either the theme is exchanged or the displayer marks itself as invalid. In the later case the displayer needs to call the `discard` method of any `DockableDisplayerListener` that was added to it.

Clients are free to implement new displayers or extend existing displayers. Any new displayer should be a focus-cycle-root, assuming the displayer uses `Swing`-components the code below can be used to setup the correct focus management:

```
1 // the new displayer
2 DockableDisplayer displayer = ...
3
4 JComponent root = (JComponent)displayer.getComponent();
5
6 root.setFocusable( true );
7 root.setFocusCycleRoot( true );
8 root.setFocusTraversalPolicy(
9     new DockFocusTraversalPolicy(
10         new DisplayerFocusTraversalPolicy( displayer ), true ));
```

6.3 Custom Theme

With the exception of the classes that are directly related to a `DockTheme` no code in the framework depends on a special undocumented behavior of a theme. Clients can reimplement the interface `DockTheme` without fear to break things.

A better approach then full reimplementation might be to extend the class `BasicTheme`. This class provides some default values which can easily be changed by the appropriate `setXYZ` method.

`DockTheme` has a method `install`, this method can be used to exchange some values that are not stored in the `DockTheme` itself. For example to exchange icons in the `IconManager`.



A theme dives deep into the framework. Implementing a new theme requires a lot of time and a good understanding of the framework. This document might help to understand the basics, but some stuff can only be found out by looking directly at the source code.

7 Drag and Drop

To drag a **Dockable** to a new location and drop it there is the most important feature of any docking framework. Surprisingly the implementation of this part is very small.

7.1 Relocator

The sourcecode that detects drag gestures, searches for the target station and makes sure that the user has some visual feedback is located in the **DefaultDockRelocator**. **DefaultDockRelocator** itself extends from **DockRelocator** which just allows to register some listeners and set some useful properties. Clients seldomly need to implement a new **DockRelocator**. If they do, then they have to implement a new **DockControllerFactory**. The code will look like this:

```
1 public class MyDockControllerFactory extends
    DefaultDockControllerFactory {
2     @Override
3     public DockRelocator createRelocator( DockController controller ) {
4         return new MyDockRelocator();
5     }
6 }
```

This factory has then to be given to the constructor of a **DockController**. For the remainder of this chapter it is assumed, that the default relocator is in use.

The **DockRelocator** that is in use can be accessed through the method **getRelocator** of **DockController**.

7.2 Sources

The relocator needs to know where and when the user presses and moves the mouse. There is more than one solution for this problem.

7.2.1 DockElementRepresentative

A **DockElementRepresentative** is a **Component** which represents a **Dockable**. Anyone can add **MouseListener**s to a representative and hence be informed about anything the mouse does on top of such a **Component**.

DockTitle and **Dockable** are two implementations of **DockElementRepresentative**. Their registration is handled automatically. If clients implement a new representative then they should call the methods **addRepresentative** and **removeRepresentative** of **DockController** to install or uninstall the representative.



DockElementRepresentative was added late to the framework. It carries some legacy code: the method **isUsedAsTitle**. This method introduces a distinction between those representations for which all features are activated (e.g. popup menus) and those for which only a selected subset is available. Normally clients implement representatives that are used as title and can return **true** here.



The behavior for representations of `Dockables` that are not registered is unspecified. Clients should not add a `DockElementRepresentative` if its `Dockable` is unknown to the `DockController`.

7.2.2 Remote control

Sometimes it is not possible to implement a `DockElementRepresentative`. Remote control of a relocator is an alternative for these cases. Remote control is realized by the classes `RemoteRelocator` and `DirectRemoteRelocator`.

A `RemoteRelocator` can be obtained by calling `createRemote` of `DockRelocator`. `RemoteRelocator` should be used in combination with a `MouseListener` and a `MouseMotionListener`:

- `MouseListener.mousePressed` → `RemoteRelocator.init`
- `MouseMotionListener.mouseDragged` → `RemoteRelocator.drag`
- `MouseListener.mouseReleased` → `RemoteRelocator.drop`

The methods `init`, `drag` and `drop` return a `Reaction`. The reaction tells the caller what to do next:

- `CONTINUE`: the operation continues, the event was ignored.
- `CONTINUE_CONSUMED`: the operation continues, the event was consumed. The caller should invoke `MouseEvent.consume`.
- `BREAK`: the operation was canceled, the event was ignored.
- `BREAK_CONSUMED`: the operation was canceled, the event was consumed. The caller should invoke `MouseEvent.consume`.

A `DirectRemoteRelocator` can be obtained by calling `createDirectRemote` of `DockRelocator`. A `DirectRemoteRelocator` is basically the same as a `RemoteRelocator` but always assumes that the user pressed the correct button on the mouse. Its methods do not return a `Reaction` because it would always be the same.



Clients can use several remote controls at the same time, they will cancel out each other if necessary. A `RemoteRelocator` can be used several times.

7.3 Destinations

A relocator needs to find the one `DockStation` on which the `Dockable` is dropped.

7.3.1 Search

The `DefaultDockRelocator` searches the destination anew whenever the mouse is moved. The search includes these steps:

1. An ordered list of all potential destinations is built. A `DockStation` is a potential destination if it is visible (`isStationVisible` of `DockStation`), not the dragged `Dockable` nor one of its children, and its boundaries contain the location of the mouse (`getStationBounds` of `DockStation`). The order depends on parent-child relations between the stations, between the `Windows` on which the stations are, and on custom conditions that every station can offer (`canCompare` and `compare` of `DockStation`).
2. Then the method `prepareMove` or `prepareDrop` of `DockStation` is called. These methods check whether the station really is a good destination. They return `true` if so, `false` if not. The first station that returns `true` is the destination.
3. The method `draw` of the new destination is called, the method `forget` on the old destination. The new destination will paint some markings to give a visual feedback to the user, the old destination will delete all the information about any drag and drop operation.



There is more information about the exact semantics in the API-documentation for `DockStation`.



Due to the varieties of stations a general interface for drag and drop would be very hard to come up with. Hence most of the work has to be done by the stations itself. This might lead to code that is written twice, but also allows much freedom in writing stations. There are some helper classes that can help with the most common tasks:

- `DockController.getAcceptance` to access all the global acceptance tests at once.
- `StationPaint`, accessible through `DockUI.getPaint`.

7.3.2 Drop

The moment a user releases the mouse and drops a `Dockable` the method `move` or `drop` of `DockStation` is called. These methods can either put the `Dockable` somewhere onto the station or merge the `Dockable` with an existing child of the station (sometimes referred as “put” and “merge” action). The results of the first reaction depend on the kind of station. The results of the second reaction are independent of the kind of station.

Merging normally results in creating a new `StackDockStation`. The existing child and the dropped `Dockable` are put onto that new station. Then

the `StackDockStation` is put at the place where the existing child was. Creation of “merged Dockables” is handled by a `Combiner`, per default by the `BasicCombiner`. Many `DockStations` have a method that allows clients to set their own implementation of a `Combiner`. Clients can exchange the `Combiner` globally by creating a new `DockTheme`, overriding the method `getCombiner` and then registering a new instance at the `DockController` through `setTheme`. Note that all descendants of `BasicDockTheme` have a method called `setCombiner` that exchanges the `Combiner` directly without the need to override `getCombiner`.



Exchanging a `Combiner` does not affect any existing `Dockable` or `DockStation`, it will only affect the creation of new elements.

7.4 Influences

There are a number of factors that can influence the search for a new destination. Some of them are customizable.

7.4.1 Modes

A `DockRelocator` can have “modes”. A mode is some kind of behavior that is activated when the user presses a certain combination of keys. Modes are modeled by the class `DockRelocatorMode`. It is not specified what effect a mode really has, but normally a mode would add some restrictions where to put a `Dockable` during drag and drop. `DockRelocatorModes` can be added or removed to a `DockRelocator` by the methods `addMode` and `removeMode`.

Currently two modes are installed:

`DockRelocatorMode.SCREEN_ONLY` (press key *shift*) ensures that a `Dockable` can only be put on a `ScreenDockStation`. That means that a `Dockable` can be directly above a `DockStation` like a `SplitDockStation`, but can’t be dropped there.

`DockRelocatorMode.NO_COMBINATION` (press key *alt*) ensures that a `Dockable` can’t be put over another `Dockable`. That means, every operation that would result in a merge is forbidden. Also dropping a `Dockable` on already merged `Dockables` will not be allowed.



The keys that have to be pressed to activate `SCREEN_ONLY` or `NO_COMBINATION` are the properties `SCREEN_MASK` and `NO_COMBINATION_MASK`. They can be changed by accessing the `DockProperties`.

7.4.2 Restrictions

The set of possible destinations for a `Dockable` can be restricted. There are several reasons why a client or the framework itself would do that:

- Some `Dockable` must always be visible.

- Some **DockStations** represent a special area that can only be used by a subset of **Dockables**.
- Some **Dockables** can only be presented on a certain kind of **DockStation**.

These restrictions are implemented through acceptance tests. An acceptance test either checks one “put” or one “merge” action. Tests can be stored at various locations:

- Every **Dockable** has two methods called **accept**.
- Each **DockStation** has a method **accept**. This method tells whether some **Dockable** can become a child of the **DockStation**. This method checks “put” and “merge” actions at the same time.
- And then there are **DockAcceptances**. A **DockAcceptance** has **accept**-methods too. These methods get a **DockStation** and some **Dockables**, and then have to decide whether the elements can be put together. Each **DockAcceptance** works on a global scale, and thus they are registered at the **DockController** through **addAcceptance**.



Acceptance tests are very powerful. They have to be implemented carefully or the drag and drop mechanism might become crippled.



Acceptance tests are performed by the potential destination **DockStation**. The **DockStation** is the first module that knows where a **Dockable** will land. Handling acceptance tests allows the station to cut down the amount of work it does, and to try alternative actions (e.g. a “put” instead of a “merge” action) if some future configuration does not pass the tests. The drawback is, that a **DockStation** can break the mechanism by just not performing the tests.

8 Preferences

The preference system allows the user to change settings which are otherwise not accessible. An example would be the shortcut for maximizing a **Dockable** (**ctrl+m**). The preference system makes a sharp distinction between model and view, clients are free to integrate the model in their own view, or to create a new model and using the standard view. Figure 7 shows the simple version of the standard view with some random preferences.




Figure 7: The **PreferenceDialog** showing some random preferences.

8.1 Model

This section explains how the model is organized.

8.1.1 Preference

A preference is an abstract concept. One preference represents some property of the framework (or of the client). A preference is a set of meta-informations about a property:

Path A unique identifier

TypePath Tells how to work with **Value**. For example how to present the value to the user (as text, as image...) or how to store the value. An object of type **Path** is used to represent the **TypePath**.

Value The current value of the property.

ValueInfo Information about the value, e.g. the maximum value for an **Integer**-property. The exact meaning of this information depends on the **TypePath**.



Value is some **Object** and **TypePath** tells the view how to cast **Value** in order to use it. If **TypePath** were a **Class** then there would never be doubt whether the correct cast is performed. But **TypePath** is a **Path** and hence an additional indirection is introduced.

The reason for this is that the same **Object** might need different treatment in different situations. E.g. an **Integer** could just be an **int**, it could be a natural number or it could be an **int** from the range 1 to 100.



There is an interface **Preference** and a class **DefaultPreference** which bring this preference-abstraction to code. It is not necessary to use them, they are just here to simplify things.

8.1.2 PreferenceModel

The **PreferenceModel** is the basic module of the preference system. A **PreferenceModel** is a list of preferences (the abstraction, not the interface). It often acts as mediator between some unspecified storage mechanism for properties and the user interface. The methods **read** and **write** are used to access that covered storage mechanism. To transfer values into the model **read** is called, to transfer values to the storage mechanism **write** is called.



DefaultPreferenceModel is the standard implementation of **PreferenceModel**. Its entries are objects of type **Preference**. Several models can be combined using a **MergedPreferenceModel**.



There are several subclasses of **DefaultPreferenceModel** for various settings that can be made. For example **EclipseThemeModel** handles properties of **EclipseTheme**. There are also many implementations of **Preference** for various properties of the framework. The API-documentation reveals more.

8.1.3 PreferenceTreeModel

This model is a **PreferenceModel** and a `javax.swing.TreeModel`. If seen as **PreferenceModel**, then it behaves like a **MergedPreferenceModel**. If seen as **TreeModel**, then it contains **PreferenceTreeModel.Node**-objects. A node can either be just a name, or another **PreferenceModel**. This model is intended to be used in a **JTree** where the user can select one aspect of the whole set of preferences to show.



The subclass **DockingFramesPreferenceModel** is the set of preferences which includes all the aspects of the core-library.

8.2 View

A **PreferenceModel** is best displayed in a **PreferenceTable**. This table will show a label, an editor and operations for each preference.

A **PreferenceTreeModel** can be displayed in a **PreferenceTreePanel**. It will show not only a **PreferenceTable** but also a **JTree** where the user can select which sub-model to edit.

Further more the `PreferenceDialog` and the `PreferenceTreeDialog` are available. These dialogs offer the options to apply the settings, to cancel editing and to reset all preferences to their default value.

8.2.1 Editors

Since there are different types of preferences, different editors are needed. The kind of editor for one preference is determined by the type-path (`getTypePath` in a model). Clients can add new editors to a `PreferenceTable` through the method `setEditorFactory`.

An editor is always of type `PreferenceEditor`. Each editor gets a `PreferenceEditorCallback` with which it can interact with the table. Whenever the user changes the editors value, the editor should call the method `set` of `PreferenceEditorCallback` to make sure the new value gets stored.

8.2.2 Operations

There are some operations which should be available for almost any preference. For example *set a default value* or *delete the current value*. The preference system introduces the `PreferenceOperation` to handle these kind of actions.

A `PreferenceOperation` is nothing more than a label and an icon. The logic for an operation is either in an editor or in a model.

Editor: Editors with operations must call the method `setOperation` of `PreferenceEditorCallback` for each operation they offer. By calling `setOperation` more than once, the editor can change the enabled state of the operation. If the user triggers an operation of the editor, the method `doOperation` of `PreferenceEditor` is called. It is then the editors responsibility to handle the operation.

Preference: Preferences can have operations as well. The method `getOperations` of `PreferenceModel` will be called once to get all the available operations for one preference. The method `isEnabled` will be invoked to find out whether an operation is enabled or not. Models can change the enabled state by calling `preferenceChanged` of `PreferenceModelListener`. If the user triggers an operation, `doOperation` of `PreferenceModel` will be invoked.

If an editor and a preference share the same operations, then per definition the operations belong to the editor. All settings from the model will just be ignored.



Operations might be confusing at first, but they can be really useful. The strength of operations is that they are handled automatically, and that they need not much code.

8.3 Storage

The `PreferenceStorage` can be used to store `PreferenceModels` in memory or persistent either as byte-stream or as XML.

The normal way to write a model from memory to the disk looks like this:

```

1 // the stream we want to write into
2 DataOutputStream out = ...
3
4 // the model we want to store
5 PreferenceModel model = ...
6
7 // And now store the model
8 PreferenceStorage storage = new PreferenceStorage();
9 storage.store( model );
10 storage.write( out );

```

Note that there are two phases in writing `model`. First the model gets **stored** (line 9) into **storage**. It is possible to store more than just one model in a **PreferenceStorage**. Second **storage** gets written onto the disk in line 10.

The standard way to read a model are to apply the same steps in reverse:

```

1 // the source of any new data
2 DataInputStream in = ...
3
4 // the model we want to load
5 PreferenceModel model = ...
6
7 // And now load the model
8 PreferenceStorage storage = new PreferenceStorage();
9 storage.read( in );
10 storage.load( model, false );

```

Like writing this operation has two phases. In line 9 **storage** gets filled with information, in line 10 the information gets transferred to **model**. The argument `false` is a hint what to do with missing preferences. In this case missing preferences are just ignored. A value of `true` would force them to become `null`.

There are some preferences which do not need to be stored by the **PreferenceStorage** because they are already stored by the underlying system. These preferences are called *natural*, while the others are called *artificial*. The method `isNatural` of **PreferenceModel** can be used to distinguish them.



The distinction between natural and artificial preferences might seem curious. But actually this allows to use an unlimited number of storage mechanisms at the same time.

8.4 Lifecycle

This section describes the best way how to use a **PreferenceModel**.

The correct lifecycle of a **PreferenceModel** includes normally these steps:

1. Create the model. Set up all the preferences that are used by the model.
2. Call `load` on a **StoragePreference**.
3. Call `write` on the model to synchronize the model with the underlying system.
4. (work with the underlying system)
5. To work with the model: call first `read`, then make the changes in the model, then call `write`.
6. (work with the underlying system)

7. Call `read` on the model to synchronize the model with the underlying system.

8. Store the model using `store` of a `PreferenceStorage`.

If the `PreferenceStorage` used in step 2 is empty because its `read` or `readXML` method failed, then calling `read` of `PreferenceModel` would at least load some default settings.

Steps 4, 5, 6 can be cycled as many times as needed.

An additional step 0 and 9 would be to read and write the `PreferenceStorage` when starting up or shutting down the application.

9 Extensions

Extensions allow libraries to add new code to the framework, this code will be treated as if it were always part of the framework. Basically it is a plug-in mechanism. Currently there are not many points where an extension can be inserted, new extension-points will be added when needed.

Extensions are collected by the **ExtensionManager**. Any module can call **load** to load extensions that match some **ExtensionName**.



Extensions were introduced in 1.0.8 to allow the usage of the glass-components. The glass-components could not be added directly to the framework due to licencing issues.

9.0.1 Glass Extension

The glass-extension adds new icons and a new way to paint tabs to the **EclipseTheme**. Clients only need to ensure that the libraries **extensionGlass.jar** and **glasslib.jar** are part of the classpath. The **ExtensionManager** will then automatically load this extension.



The Glass Extension is licensed by a modified version of the LGPL. You are prohibited to use the library if your application provides “pornography, racialistics, violence, or the like material”. (A note by the author of this document: This licence may prohibit a photo-editing tool, an email-client used by atheists, or any software used by the police.)

9.0.2 Extension Points

A number of extensions exists. The following list only includes the extensions of the **Core** library.

ChoiceExtension

Name **ChoiceExtension.CHOICE_EXTENSION**

Usage Allows to add additional entries to a **Choice**. A **Choice** is a preference allowing the user to pick one of many items.

DockThemeExtension

Name **DockThemeExtension.DOCK_THEME_EXTENSION**

Usage Allows to modify a **DockTheme** during the installation process.

ColorScheme

Name **ColorScheme.EXTENSION_NAME**

Usage Allows to extend or override the contents of a **ColorScheme**.

10 Properties

There are a number of interesting settings whose effects are deeply hidden within the framework. Properties are an easy way to access these settings and change them. Properties are represented by the class `DockProperties` which can be accessed through `getProperties` of `DockController`.

`DockProperties` is nothing else than a map. Instances of `PropertyKey` are used as keys. The type of the value depends on the key and the map is typesafe. With the help of a `DockPropertyListener` any object can be informed immediately when a value changes.

There are a number of keys and the remainder of this chapter will list all of the keys that are present in version 1.0.8. If not explicitly said otherwise, then any change in the properties will have an immediate effect.



Some of these properties are accessed and changed by `DockThemes`.

10.1 Themes

BasicTheme.BASIC_COLOR_SCHEME

Type `ColorScheme`

Default An instance of `BasicColorScheme`

Usage The `ColorScheme` used by `BasicTheme`.

BubbleTheme.BUBBLE_COLOR_SCHEME

Type `ColorScheme`

Default An instance of `BubbleColorScheme`

Usage The `ColorScheme` used by `BubbleTheme`.

FlatTheme.FLAT_COLOR_SCHEME

Type `ColorScheme`

Default An instance of `FlatColorScheme`

Usage The `ColorScheme` used by `FlatTheme`.

EclipseTheme.ECLIPSE_COLOR_SCHEME

Type `ColorScheme`

Default An instance of `EclipseColorScheme`

Usage The `ColorScheme` used by `EclipseTheme`.

EclipseTheme.PAINT_ICONS_WHEN_DESELECTED

Type `Boolean`

Default `false`

Usage Whether to paint icons in tabs of `Dockables` that are not selected.
This setting might be ignored if a custom `TabPainter` is applied.

EclipseTheme.TAB_PAINTER

Type `TabPainter`

Default `ShapedGradientPainter.FACTORY`

Usage How to paint tabs in `EclipseTheme` for `Dockables`.

EclipseTheme.THEME_CONNECTOR

Type `EclipseThemeConnector`

Default An instance of `DefaultEclipseThemeConnector`

Usage Tells how a lonely `Dockable` gets presented in `EclipseTheme`.
Whether it has a border and a title. Also tells which `DockActions` are to be shown on tabs. Changing this entry will not affect decisions that were made by the previous connector.

SingleTabDecider.SINGLE_TAB_DECIDER

Type `SingleTabDecider`

Default `SingleTabDecider.NONE`

Usage Tells whether a single tab should be painted for some `Dockables`.
This makes the `Dockables` look as if they were a child of a `StackDockStation` even if there is no such station around.

DockTitle.ORIENTATION_STRATEGY

Type `OrientationToRotationConverter`

Default `OrientationToRotationConverter.DEFAULT`

Usage Tells how to rotate text on a `DockTitle`.

10.2 Stations

FlapDockStation.LAYOUT_MANAGER

Type `FlapLayoutManager`

Default An instance of `DefaultFlapLayoutManager`

Usage Tells the initial size and whether to hold a `Dockable` in a `FlapDockStation`. The default setting uses the same size for all `Dockables` and forgets the hold-property as soon as a `Dockable` is removed from the station.

FlapDockStation.BUTTON_CONTENT

Type `ButtonContent`

Default `ButtonContent.THEME_DEPENDENT`

Usage Tells which information to display on the buttons that represent `Dockables` on a `FlapDockStation`. Any mix of icons, text and `DockActions` is possible.

FlapDockStation.MINIMUM_SIZE

Type Dimension

Default 10, 10

Usage The minimal size of a `FlapDockStation` if it does not have any children.

ScreenDockStation.BOUNDARY_RESTRICTION

Type `BoundaryRestriction`

Default `BoundaryRestriction.FREE`

Usage Decides about the shape and location a `ScreenDockWindow` is allowed to have. E.g. `BoundaryRestriction` might force windows to be visible only on one of many screens.

ScreenDockStation.WINDOW_FACTORY

Type `ScreenDockWindowFactory`

Default An instance of `DefaultScreenDockWindowFactory`

Usage The factory used to create new windows for `ScreenDockStation`. Changing this property has no effect on existing windows. `DefaultScreenDockWindowFactory` can be customized and should be preferred over newly written factories.

ScreenDockStation.EXPAND_ON_DOUBLE_CLICK

Type Boolean

Default true

Usage Whether a double click onto a title changes the fullscreen-mode of a child of a `ScreenDockStation`.

ScreenDockStation.FULL_SCREEN_STRATEGY

Type `ScreenDockFullscreenStrategy`

Default An instance of `DefaultScreenDockFullscreenStrategy`

Usage Defines how a full-screen window looks like and how to switch between normal and full-screen mode.

StackDockStation.COMPONENT_FACTORY

Type `StackDockComponentFactory`

Default null

Usage Tells a `StackDockStation` how to arrange its children.

StackDockStation.TAB_CONTENT_FILTER

Type `TabContentFilter`

Default null

Usage Allows to influence what content a tab on a `StackDockStation` contains. Does not apply on tabs that were created because of a `SingleTabDecider`.

TabPane.LAYOUT_MANAGER

Type TabLayoutManager

Default Depends on the current theme

Usage Tells how to order the tabs on a `StackDockStation`. Warning: some `StackDockComponents` do not support all the features a layout manager may require.

CombinedMenuContent.MENU_CONTENT

Type CombinedMenuContent

Default an instance of `PopupCombinedMenuContent`

Usage Tells how to present the content of the `Dockable-selection-menu` that is used by a `StackDockStation` if not all tabs are visible.

SplitDockStation.MAXIMIZE_ACCELERATOR

Type KeyStroke

Default ctrl+m

Usage The keys that have to be pressed in order to maximize or normalize a child of `SplitDockStation`.

SplitDockStation.LAYOUT_MANAGER

Type SplitLayoutManager

Default An instance of `DefaultSplitLayoutManager`

Usage The `SplitLayoutManager` is responsible to handle most of the actions that can change the layout of a `SplitDockStation`

PlaceholderStrategy.PLACEHOLDER_STRATEGY

Type PlaceholderStrategy

Default null

Usage Maps `Dockables` to placeholders allowing the layout to be much more stable when removing and adding `Dockables`. Affects all stations.

10.3 Controlling

DockableSelector.INIT_SELECTION

Type KeyStroke

Default ctrl+shift+e

Usage Hitting these keys will open a window where the user can select the focused `Dockable`.

DockRelocatorMode.SCREEN_MASK

Type ModifierMask

Default shift

Usage If these modifiers are pressed during a drag and drop operation then `DockRelocatorMode.SCREEN_ONLY` gets activated. This will force the `Dockable` to be dropped onto a `ScreenDockStation`.

DockRelocatorMode.NO_COMBINATION_MASK

Type `ModifierMask`

Default `alt`

Usage If these modifiers are pressed during a drag and drop operation then `DockRelocatorMode.NO_COMBINATION` gets activated. This will prevent the dropped `Dockable` from merging with another `Dockable`.

DockFrontend.HIDE_ACCELERATOR

Type `KeyStroke`

Default `ctrl+F4`

Usage If a `DockFrontend` is in use then hitting these keys will hide the currently focused `Dockable`.

10.4 Legacy

AWTComponentCaptureStrategy.STRATEGY

Type `AWTComponentCaptureStrategy`

Default `PAINT_ALL_STRATEGY`

Usage Tells how the framework can take a picture from a `Component` that is or contains an `AWT-Component`. Different strategies are available, some are more subtle but efficient, others are blunt but working under harsh conditions.

10.5 Gimmicks

PropertyKey.DOCKABLE_ICON

Type `Icon`

Default `null`

Usage This icon is shown for any `Dockable` that has no icon set.

PropertyKey.DOCKABLE_TITLE

Type `String`

Default `null`

Usage This text is shown for any `Dockable` that has no title set.

PropertyKey.DOCKABLE_TOOLTIP

Type `String`

Default `null`

Usage This text is shown for any `Dockable` for which no tooltip was set.

PropertyKey.DOCK_STATION_ICON

Type Icon

Default null

Usage This icon is shown for any `DockStation` that has no icon set.

PropertyKey.DOCK_STATION_TITLE

Type String

Default null

Usage This text is shown for any `DockStation` that has no title set.

PropertyKey.DOCK_STATION_TOOLTIP

Type String

Default null

Usage This text is shown for any `DockStation` for which no tooltip was set.